

## Workflow 2: Attaching the Color Table Permanently

1. To attach the correct color table more permanently, select *Workspace>Configuration...* from the main MicroStation pulldown.




Figure 7-1: Workspace Menu - Configuration

2. From the workspace configuration dialog box, select colors.




Figure 7-2: User Configuration

3. Highlight Default Color Table from the upper right window on the palette. Click on the select button

Navigate to and select the FLH common color table (Color1.tbl) from the following location: N:\V8i\_resource\FLH\_Common\MicroStation\Tables\ Once selected, click the Open button.




Figure 7-3: Select File for Default Color Table

- Once Open is selected, the user is redirected back to the Configuration dialog. Select OK. This will prompt an alert from MicroStation, asking if you really want to save changes to your .ucf file (user configuration file).




Figure 7-4: Alert Dialog Box

- Choose the Yes button and the color table will be attached each time MicroStation is launched. For all configuration changes, exit MicroStation and re-enter for the changes to take effect.



Workflow 2 - Attaching the Color Table Permanently is for information only. CFLHD designers should not manually attach or edit configuration variables. For CFLHD, the CADD Coordinator sets the configuration variables.